


Electric Dance

Featuring fabrics from Cube-bori and Jacqueline DeJonge's BeColorful collection
pattern by Heidi Pridemore of The Whimsical Workshop Workshop

size: 64" x 64"



Please Note: Quilt Image shown is a digital representation, fabric look may vary on your project.
Visit anthologyfabrics.com, Free Patterns for any pattern updates before you start your project.




812 Jersey Ave – Jersey City, NJ 07310 • 201.659.0444 • anthologyfabrics.com • info@anthologyfabrics.com



Electric Dance

Estimated Fabric Requirements:


1 panel – 15271 Multi
1 ¼ yards – 16742 Green
⅔ yard – 16740 Lime
¾ yard – 16725 Blue
⅔ yard – 16724 Royal
⅜ yard – 16735 Green
⅜ yard – 16741 Green
⅜ yard – 16737 Green
⅝ yard – 16721 Royal
4 yards – 16722 Royal




15271 Multi (A)




16742 Green (B)



16740 Lime (C)



16725 Blue (D)



16724 Royal (E)



16735 Green (F)



16741 Green (G)



16737 Green (H)



16721 Royal (I)



16722 Royal
(Backing)



Electric Dance

Cutting Instructions:

Fabric A: Cube-bori Panel 45" – Multi

- Fussy cut one 44 ½" panel.

Fabric B: Leaves – Green

- Cut four 2 ½" x WOF strips. Sew the strips together end to end with diagonal seams and cut two 2 ½" x 64 ½" strips.
- Cut four 2 ½" x WOF strips. Sew the strips together end to end with diagonal seams and cut two 2 ½" x 60 ½" strips.
- Cut three 3" x WOF strips. Sew the strips together end to end with diagonal seams and cut two 3" x 49 ½" strips.
- Cut three 3" x WOF strips. Sew the strips together end to end with diagonal seams and cut two 3" x 44 ½" strips.

Fabric C: Dots – Lime

- Cut two 6 ½" x WOF strips. Sub-cut the strips into eight 6 ½" squares.
- Cut two 3 ½" x WOF strips. Sub-cut the strips into eight 3 ½" x 6 ½" strips.

Fabric D: Dots – Blue

- Cut seven 3 ½" x WOF strips. Sub-cut the strips into eighty 3 ½" squares.

Fabric E: Seeds – Royal

- Cut six 3 ½" x WOF strips. Sub-cut the strips into sixty-four 3 ½" squares.

Fabric F: Seeds – Green

- Cut three 3 ½" x WOF strips. Sub-cut the strips into sixteen 3 ½" x 6 ½" strips.

Fabric G: Lines – Green

- Cut three 3 ½" x WOF strips. Sub-cut the strips into sixteen 3 ½" x 6 ½" strips.

Fabric H: Dots – Green

- Cut three 3 ½" x WOF strips. Sub-cut the strips into sixteen 3 ½" x 6 ½" strips.

Fabric I: Grid – Royal

- Cut seven 2 ½" x WOF strips for the binding.

Backing: Leaves – Royal

- Cut two 72" x WOF strips. Sew the strips together and trim to 72" x 72" for the pieced back.



Electric Dance

Block Assembly:

1. Sew one 3" x 44 1/2" Fabric B strip to each side of the 44 1/2" Fabric A panel. Sew one 3" x 49 1/2" Fabric B strip to the top and to the bottom of the Fabric A panel. Trim the block to measure 48 1/2" square to make the Center Block.
2. Place one 3 1/2" Fabric E square on the left side of one 3 1/2" x 6 1/2" Fabric F strip, right sides together (Fig. 2). Sew across the diagonal of the square from the upper right corner to the lower left corner (Fig. 2). Flip open the triangle formed and press (Fig. 3). Trim away the excess fabric from behind the triangle, leaving a 1/4" seam allowance.
3. Place another 3 1/2" Fabric E square on the right side of the 3 1/2" x 6 1/2" Fabric F strip, right sides together (Fig. 4). Sew across the diagonal of the square from the upper left corner to the lower right corner (Fig. 4). Flip open the triangle formed and press. Trim away the excess fabric from behind the triangle, leaving a 1/4" seam allowance to make one Unit 1 strip (Fig. 5).
4. Repeat Steps 2-3 to make sixteen Unit 1 strips total.




Fig. 1



Fig. 2




Fig. 3



Fig. 4




Fig. 5

5. Repeat Steps 2-3 using sixteen 3 1/2" x 6 1/2" Fabric H strips and thirty-two 3 1/2" Fabric E squares to make sixteen Unit 2 strips (Fig. 6).
6. Repeat Steps 2-3 using sixteen 3 1/2" x 6 1/2" Fabric G strips and thirty-two 3 1/2" Fabric D squares to make sixteen Unit 3 strips (Fig. 7).
7. Repeat Steps 2-3 using eight 3 1/2" x 6 1/2" Fabric C strips and sixteen 3 1/2" Fabric D squares to make eight Unit 4 strips (Fig. 8).




Fig. 6




Fig. 7




Fig. 8



Electric Dance

8. Place one 3 ½" Fabric D square on the top left corner of one 6 ½" Fabric C square, right sides together (Fig. 9). Sew across the diagonal of the smaller square from the upper right corner to the lower left corner (Fig. 9). Flip open the triangle formed and press (Fig. 10). Trim away the excess fabric from behind the triangle ¼" away from the sewn seam.
9. Follow Figure 11 for the seam direction to add a 3 ½" Fabric D square to each of the remaining corners of the 6 ½" Fabric C square to make one Unit 5 block (Fig. 12).
10. Repeat Steps 8-9 to make eight Unit 5 blocks total.




Fig. 9




Fig. 10




Fig. 11





Fig. 12

Quilt Assembly – Refer to the Quilt Layout while assembling the quilt top:

11. Sew four Unit 2 strips, four Unit 3 strips, four Unit 1 strips, two Unit 4 strips and one Unit 5 block together. Repeat to make a second strip. Sew one strip to each side of the Center Block. Pay attention to the orientation of the units.
12. Sew three Unit 5 blocks, four Unit 2 strips, four Unit 3 strips, four Unit 1 strips and two Unit 4 strips together. Repeat to make a second strip. Sew the strips to the top and to the bottom of the Center Block. Pay attention to the orientation of the units.
13. Sew one 2 ½" x 60 ½" Fabric B strip to each side of the Center Block. Sew one 2 ½" x 64 ½" Fabric B strip to the top and to the bottom of the Center Block to make the quilt top.
14. Layer and quilt as desired.
15. Sew the seven 2 ½" x WOF Fabric I strips together, end to end with 45-degree seams, to make the binding. Fold this long strip in half, lengthwise with wrong sides together, and press.
16. Bind as desired.



Electric Dance



Be sure to visit www.windhamfabrics.com to see the complete collection and to download other FREE Projects